

APPS-FABINDIA OVERSEAS PVT.RETAIL-FPP

USER MANUAL

Installing Fopl Erp Application

Version 1.0

13th April, 2009

Submitted to



Prepared By



Wipro Limited



Document Details

Project Name	APPS-FABINDIA OVERSEAS PVT.RETAIL-FPP
Account	Fabindia
Current Version	
List of Contributors	Wipro and Fabindia
Customer Contact Information	

Prepared By	Reviewed By	Approved by/Date
Krishna Mohan K Software Engineer Wipro	A Ravi Sankar	

Revision History

Version	Date	Description of Change	Reason for change	Affected Sections
1.0	13 th April, 2009	Initial Version		

Copyright Acknowledgment

Any registered names, trademarks and logos used in this document remain the property of the owning respective companies or organizations concerned.

Disclaimer

The documentation is prepared based on the specifications and requirements specified or disclosed to Wipro Limited by Fabindia.

TABLE OF CONTENTS

1	INTRODUCTION.....	4
2	PRE-REQUISITES.....	4
3	FOPLSERVERSETUP.....	5
3.1	VERIFYING FOPLSERVER INSTALLATION	10
4	FOPLSYNCSERVICESETUP	12
4.1	VERIFYING FOPLSYNCSERVICE	19
5	FOPLSMARTCLIENTSETUP	21
5.1	VERIFYING FOPLSMARTCLIENTSETUP.....	26

1 Introduction


This document will take the users through stepwise procedure in installing the Fopl Erp application.

2 Pre-Requisites

1. IIS should be installed
2. .Net Framework 3.5 should be installed
3. SQL Server 2005 should be installed.
4. First IIS has to be enabled, and then .Net Framework 3.5 should be installed.
5. If .Net Framework 3.5 is installed before IIS, then Foplservice may not run. In such case we need to run a command in command prompt.


C:\WINNT\Microsoft.NET\Framework\v2.0.50727\aspnet_regiis -i

6. After installing FOPLServer Go to IIS and browse the Service1.svc file (Not a pre-requisite should be checked after installing **FoplServerSetup**)



The user should be able to see the below page.

Instead of this if it is redirecting to any other page, **then remove that redirect url.**



3 FopIServerSetup.

FopI Server Set up:

Step 1:


Double click on FopIServerSetup.exe file

Click on **Run**




Step 2:

The window “Welcome to the FopI Server Setup Wizard” will be opened.
Click on **Next**




Step 3:

The window “**confirm Installation**” will be opened.
To confirm the installation click on **Next**

**Step 4:**


The window “**Installing FoplServer**” will be opened.



Here the user can see different fields like:


Server Name: Server name means Database Server Name (Database server name will be the <computer name>/<Instance Name> for example: FabIndia/SQLExpress).

- **Database Name:** The name of the Database to which the application is connecting.
- **User Name:** User name for connecting to the database.
- **Password:** Password for connecting to the Database
- After providing the details click on **Next**.



The image shows the 'FoplServer' installation window titled 'Installing FoplServer'. It contains two sections for database details. The 'Fopl Server DB Details' section has fields for Server Name (D:\WPCR007), Database Name (FabConnect_Pilot), User Name (fopluser), and Password (masked with asterisks). The 'Queue DB Details' section has fields for Server Name (D:\WPCR007), Database Name (QueueDatabase), User Name (fopluser), and Password (masked with asterisks). At the bottom are 'Cancel' and 'Next' buttons.

“Please Confirm” window will be opened.
Click on **Yes** to continue



The image shows a 'Please Confirm' dialog box with a question mark icon. The text inside says 'Are you sure you want to continue ?'. There are two buttons at the bottom: 'Yes' and 'No'.

Step 5:

After clicking on yes the user can see the below window:


Here the user can see three different entities namely:

- MRW
- SRC and
- STORE

For example if user wants to set up the machine as MRW Server.

Then follow below procedure:


- Select **MRW** and then **Select MRW Code** dropdown and select the MRW Code.(For example I'm selecting **MRW3**)
- Finally after selecting click on **Finish**



Step 6:

The below window “**Installation Complete**” will be opened.

The Installation is complete and the user can click on **Close**, to complete the installation




3.1 Verifying FoplServer Installation

Step 1:

Goto Start -> Run


Enter **inetmgr** and click on OK.



Step 2:

The window "**Internet Information Services**" will be opened.

Under Web sites-> Default Web Site there should be our folder **FoplServer**



4 FoplSyncServiceSetup

Step 1:

Double Click on **FoplSyncServiceSetup** EXE file.


Click on **Run**



Step 2:


The window “**Welcome to the FoplSyncService Setup Wizard**” will be opened.

Click on **Next**


**Step 3:**

The below window “**Select Installation Folder**” will be opened.


Here the user can select the path where the FopISyncService has to be installed by clicking on **Browse**.



In the below window I have chosen E drive and FabConnect Folder. Similarly the user can choose any location.




After choosing the folder click on **Next**




Step 4:

The window “**Confirm Installation**” will be opened.

Click on **Next**

**Step 5:**

The below window “**Installing FopISyncService**” will be opened.



Here the user can see different fields like:

Entity Details:

- **Fopl Server:** Name of the computer

Interval Updates:

- **Data:** here the user can enter the time in seconds. The time specifies the time in which the Data updates has to happen between the Central and the corresponding entity (store, src, mrw).
- **File:** here the user can enter the time in seconds. The time specifies the time in which the File update has to happen between the Central and the corresponding entity (store, src, mrw).
- **Batch:** here the user can enter the time in seconds. The time specifies the time in which the Batch update has to happen between the Central and the corresponding entity (store, src, mrw).

In the **Central Data Sync Server Name** the user has to enter the **Central Server name**.

After providing all the details click on **Finish**.


If the server is not able to communicate with the central server then you will get the below message

If you want to continue then click on yes, installation will be completed.
Note: Once the installation is completed, we need to manually enter the **Central Server name** in **FopIDataSyncConfig** file in the below node.


```
<endpoint address="net.tcp:// <Central Server
name>:57166/FopIDataSyncService" />
```

Step 6:

Click on **Close** to complete the installation.

**Step 7:**

- After Installing **FopISyncService** go to the path where **FopISyncService** is installed.
- For Example if the user has not changed the path, then default path is **C:\Program Files\Wipro Infotech\FopISyncService**
- After navigating to that path, the user can see a folder named "**download**".
- Give full sharing permission to everyone for that folder as shown below.




4.1 Verifying FopISyncService

Step 1:

Go to Start-> Run


Enter **services.msc** and press **ok**.



Step 2:

The “**Services**” window will be opened.

In services search for **FopISyncService**.



5 FopISmartClientSetup

Step 1:

Double click on **FopISmartClientSetup** EXE File.

Click on **Run**.



Step 2:


The below window **“Welcome to the FabConnect Setup Wizard”** will be opened.

Click on **Next**.



Step 3:


The window “**Select Installation Folder**” will be opened.
Here the user can select the path or simply click on **Next**.



Step 4:


The window “**Confirm Installation**” will be opened.

Click on **Next**



Step 5:

The window “**Installing FabConnect**” will be opened.



Here the user has to enter the Fopl Server Name.


Fopl Server Name is the name of the Server where the application is installed.

After entering the Fopl Server Name click on **Next**.




Step 6:

POS Configuration is enabled for Stores and disabled for SRC/MRW. Need to select the till codes for stores, if POS configuration is not required then tick the checkbox then till codes will be disabled and you can continue the installation. Click on **Finish** to continue the installation


**Step 7:**

Click on **Close** to complete the installation.



5.1 Verifying FopISmartClientSetup

After Successful installation of **FopISmartClientSetup**, we can see the **FabConnect** Short cut image.
Double click on it.



The **Login** window will be opened.
Enter the credentials and use the application.

Login

fabindia

Login Name *

Password *

☐ Remember Login

Login Cancel

[Forgot Password?](#)

Fields marked with * are required